




**DOCUMENT TO CREATE A ROLE WITH REQUIRED RFC
AUTHORIZATIONS**




Creating and Maintaining RFC USER


Transaction – SU02




Click ‘To Profile Generator’



Create Role – Click on “Role” button



Tab to “Authorization” -This will give you a pop up screen as shown above
Click yes on popup to save



Click Change Authorization Data



SAP

Change role: Authorizations

Maint.: 0 Unmaint. org. levels 0 open fields, Status: Changed

Z_GUIXTRFC Z_GUIXTRFC

Choose Template


Template	Text for Template
HR940_VACATION	HR: InfoType 2001 Subtype 0100
SAP_ADMIN_AU	Administration: Authorization data administrator
SAP_ADMIN_PR	Administration: Authorization profile administrator
SAP_ADMIN_US	Administration: User administrator
SAP_ALL	Complete authorization with all authorization objects
SAP_PRINT	Print Authorization
SAP_USER_B	Basic authorizations for users
S_RS_DME_AUTH_DISP	Data Mining - Display
S_RS_DME_AUTH_MNT	Data Mining - Maintain
S_RS_RDEAD	BW Role: Administrator (Development System)
S_RS_RDEMO	BW Role: Modeler (Development System)

Adopt reference Do not select templates


No data exists. You can choose a template.

PFCG juneau INS


Click Do not select templates



Click 'manually'




Type S_RFC , S_USER_GRP, S_USER_SYS




Click on “Open”

SYNACTIVE

Clicking on the open button gives you a screen as follows:



After you click on “open”
Click on the “write” or “change” icon shown on screen shot



Select “Execute” on the pop up screen and then click on “save” button


Similarly, the parameters for “name of RFC to be protected” and “Type of RFC to protect” could be set.

Using Existing Remote Enabled SAP Function Modules, specify the function group for those function modules (Name of RFC to be protected)

Alternatively, add the appropriate role to the RFC User

SYNACTIVE


Set parameters as shown in following screen shot



A detailed list of RFC actions and the required authorizations can be found at
http://synactive.com/docu_e/doc_rfc.html


SYNACTIVE


Click “Generate”



SYNACTIVE


Click on Save







This is a system generated Profile name; we can edit this information and text.

Click "Generate" again





Enter “SU01”, enter the username and click on “Create Role” button



Enter Last Name and First Name of the user
Tab to “Logon data” TAB



SAP

Maintain User

Address Logon data SNC Defaults Parameters Roles Profiles

User GXTRFC
Last Changed On 00:00:00 Status Not saved

Alias []

Password

Initial password [] Repeat password []

User Group for Authorization Check []

Validity Period

Valid from [] Valid through []

Other Data

Accounting Number [] Cost center []

User Type


Dialog Communications System Service Reference

SU01 juneau INS


Start SAP Logon 640 Maintain User Synactive GuiXT Document1 - Micro... RFC (Remote Fun... 4:47 PM

Enter the password


Choose “communications” radio button in the “user type” group box




Tab to the “Role” TAB
Goto Role tab and add the role we just created Z_GUIXTRFC



Goto "Profile" tab and Check the profile by double-clicking or detail on the profile



Verify the Authorizations



Save the user